

Yubico Universal 2nd Factor C Library

COLLABORATORS

	<i>TITLE :</i> Yubico Universal 2nd Factor C Library		
<i>ACTION</i>	<i>NAME</i>	<i>DATE</i>	<i>SIGNATURE</i>
WRITTEN BY		July 13, 2019	

REVISION HISTORY

NUMBER	DATE	DESCRIPTION	NAME

Contents

1	Yubico Universal 2nd Factor C Library	1
1.1	u2f-host	1
1.2	u2f-host-types	1
1.3	u2f-host-version	3
2	Index	5

Chapter 1

Yubico Universal 2nd Factor C Library

This is a C library that implements the host-side of the U2F protocol. More precisely, it provides an API for applications that wishes to talk to a U2F device and perform the U2F Register and U2F Authenticate operations.

1.1 u2f-host

u2f-host —

Description

Functions

Types and Values

1.2 u2f-host-types

u2f-host-types —

Types and Values

enum	u2fh_rc
enum	u2fh_initflags
enum	u2fh_cmdflags
typedef	u2fh_devs

Description

Functions

Types and Values

enum u2fh_rc

Error codes.

Members

U2FH_OK	Success.
U2FH_MEMORY_ERROR	Memory error.
U2FH_TRANSPORT_ERROR	Transport (e.g., USB) error.
U2FH_JSON_ERROR	Json error.
U2FH_BASE64_ERROR	Base64 error.
U2FH_NO_U2F_DEVICE	Missing U2F device.
U2FH_AUTHENTICATOR_ERROR	Authenticator error.
U2FH_TIMEOUT_ERROR	Timeout error.
U2FH_SIZE_ERROR	

enum u2fh_initflags

Flags passed to `u2fh_global_init()`.

Members

U2FH_DEBUG	Print debug messages.
------------	-----------------------

enum u2fh_cmdflags

Flags passed to `u2fh_register()` and `u2fh_authenticate()`.

Members

U2FH_REQUEST_USER_PRESENCE	Request user presence.
----------------------------	------------------------

u2fh_devs

```
typedef struct u2fh_devs u2fh_devs;
```

1.3 u2f-host-version

u2f-host-version —

Functions

const char *

| u2fh_check_version ()

Types and Values

#define	U2FH_VERSION_STRING
#define	U2FH_VERSION_NUMBER
#define	U2FH_VERSION_MAJOR
#define	U2FH_VERSION_MINOR
#define	U2FH_VERSION_PATCH

Description

Functions

u2fh_check_version ()

```
const char~*  
u2fh_check_version (const char *req_version);
```

Check that the version of the library is at minimum the requested one and return the version string; return NULL if the condition is not satisfied. If a NULL is passed to this function, no check is done, but the version string is simply returned.

See **U2FH_VERSION_STRING** for a suitable *req_version* string.

Parameters

req_version

| Required version number,
| or NULL.

|

Returns

Version string of run-time library, or NULL if the run-time library does not meet the required version number.

Types and Values

U2FH_VERSION_STRING

```
#define U2FH_VERSION_STRING "1.1.10"
```

Pre-processor symbol with a string that describe the header file version number. Used together with `u2fh_check_version()` to verify header file and run-time library consistency.

U2FH_VERSION_NUMBER

```
#define U2FH_VERSION_NUMBER 0x01010a
```

Pre-processor symbol with a hexadecimal value describing the header file version number. For example, when the header version is 1.2.3 this symbol will have the value 0x01020300. The last two digits are only used between public releases, and will otherwise be 00.

U2FH_VERSION_MAJOR

```
#define U2FH_VERSION_MAJOR 1
```

Pre-processor symbol with a decimal value that describe the major level of the header file version number. For example, when the header version is 1.2.3 this symbol will be 1.

U2FH_VERSION_MINOR

```
#define U2FH_VERSION_MINOR 1
```

Pre-processor symbol with a decimal value that describe the minor level of the header file version number. For example, when the header version is 1.2.3 this symbol will be 2.

U2FH_VERSION_PATCH

```
#define U2FH_VERSION_PATCH 10
```

Pre-processor symbol with a decimal value that describe the patch level of the header file version number. For example, when the header version is 1.2.3 this symbol will be 3.

Chapter 2

Index

U

u2fh_check_version, [3](#)

u2fh_cmdflags, [2](#)

u2fh_devs, [3](#)

u2fh_initflags, [2](#)

u2fh_rc, [1](#)

U2FH_VERSION_MAJOR, [4](#)

U2FH_VERSION_MINOR, [4](#)

U2FH_VERSION_NUMBER, [4](#)

U2FH_VERSION_PATCH, [4](#)

U2FH_VERSION_STRING, [3](#)